# Wikiprint Book

Title: EcomsUdg/RPackage/Functions

Subject: TracMeteo - EcomsUdg/RPackage/Functions

Version: 44

Date: 11/30/2021 04:25:39 PM

# **Table of Contents**

makeNcmlDataset	3
dataInventory	3
loadObservations	4
loadData	4
loadSystem4	4

### makeNcmlDataset

#### **Description**

Generates a NcML file from a collection of netCDF files.

#### Usage

makeNcmlDataset(source.dir, ncml.file)

### <u>Arguments</u>

- source.dir: character string indicating a valid path of the directory containing the files
- ncml.file: character string indicating the NcML file name (and path, default to working directory), including the extension .ncml.

The output is a NcML file named as file.name which will be stored in the output.dir.

#### <u>Details</u>

- All files of the same dataset should be put together in the same directory, indicated by the source.dir argument.
- Currently the function works only with netCDF (.nc) file collections.
- · A number of useful recommendations regarding dataset naming are provided ?here

#### Value

Creates a NcML file at the specified location

### <u>Notes</u>

A NcML file is a <a href="mailto:reversions">?XML</a> representation of netCDF metadata. This is approximately the same information one gets when dumping the header of a netCDF file (e.g. by typing on the terminal the command ncdump -h). By means of NcML it is possible to create virtual datasets by modifying and aggregating other datasets, thus providing maximum flexibility and ease of access to data stored in collections of files containing data from different variables/time slices. The function <a href="mailto:makeNcmlDataset">makeNcmlDataset</a> is intended to deal with reanalysis, forecasts and other climate data products, often consisting of collections of netCDF files corresponding to different variables and partitioned by years/decades or other time slices. It operates by applying to types of <a href="mailto:readform:readform:">readform:re

- 1. Union: Performs the union of all the dimensions, attributes, and variables in multiple NetCDF files
- 2. JoinExisting: Variables of the same name (in different files) are connected along their existing, outer dimension, called the aggregation dimension. In this case the aggregation dimension is *time*.

### dataInventory

### **Description**

Provides summary information about the main characteristics of a NcML dataset.

### Usage

dataInventory(ncml.file)

### **Arguments**

ncml.file: a character string indicating the full path to the virtual dataset (the NcML file). This can be either a path containing the directory and name of the file, or an appropriate URL in case the dataset is remotely accessed (e.g., via the <a href="#specific support of the file">Specs-EUPORIAS THREDDS</a>).

### <u>Value</u>

The output of the function consists of a list of variable length, depending on the number of variables contained in the dataset, following this structure:

- Description: Description of the variable
- DataType: Character string indicating data type (i.e. float ...)
- Units: Character string indicating the units of the variable

- TimeStep: A difftime class object representing the time interval between consecutive values in the time dimension axis Dimensions: A list of length *n*, containing the following information for each of the *n* dimensions:
  - Type: Character vector indicating the type of dimension (e.g. Time, Lon, Pressure ...)
  - Units: Character vector indicating the units of the dimension axis
  - Values: A vector containing all the dimension values. This might be a vector of POSIX1t class in case of a dimension of type time, or numeric in other cases.

### Details

A common need prior to data analysis is to get an overview of all data available and their structure (variables, dimensions, units, geographical extent, time span ...). Note that the function provides an overview of the raw data as they are stored in the original data files. The units may change after loading the function if conversions are applied via dictionary.

# loadObservations

### Description

Loads observational station data from standard station datasets stored in .csv files

#### Usage

loadObservations(source.dir, var, standard.vars=TRUE, stationID, startDate=NULL, endDate=NULL)

### **Arguments**

- source.dir: Character string indicating the full path to the directory where the data are stored (see Details).
- · var: Character string indicating the variable to load.
- standard.vars: Logical. Default to FALSE. If TRUE a dictionary must be available (see Details)
- stationID: Character string indicating the identification code of the station.
- startDate: Optional character string in the form "Year-month-day" (e.g. "1950-01-01") indicating the starting day of the time series to retrieve.
   Default to first record available.
- endDate: Optional character string in the form "Year-month-day" (e.g. "2000-12-31") indicating the last day of the time series to retrieve. Default to last record available.

### <u>Details</u>

This function works with standard .csv observational datasets. The dictionary is the table that translates the variable as stored in the dataset to the standard variables defined in the vocabulary. More details <a href="https://example.com/?here">https://example.com/?here</a>

### Value

### **loadData**

Description

<u>Usage</u>

<u>Arguments</u>

<u>Details</u>

<u>Value</u>

### loadSystem4

### Description

Loads hindcast/forecast data from ECMWF's System4 model by remotely accessing the SPECS-EUPORIAS THREDDS Data Server.

# Usage

loadSystem4(dataset, var, members, lonLim, latLim, season, years, leadMonth)

### <u>Arguments</u>

- dataset: A character string indicating the full URL path to the OPeNDAP dataset. Currently, the accepted values correspond to the System4
   ?available datasets at the SPECS-EUPORIAS THREDDS Data Server.
- var: Variable code (see Details).
- members: Optional. A vector of integers indicating the members to be loaded. Default to NULL, which loads all members available. For instance, members=1:5 will retrieve the first five members.
- lonLim: Vector of length = 2, with minimum and maximum longitude coordinates, in decimal degrees, of the bounding box selected.
- latLim: Vector of length = 2, with minimum and maximum latitude coordinates, in decimal degrees, of the bounding box selected.
- season: A vector of integers specifying the desired season (in months, January=1 ...). Options include one to several months. If NULL (the default), the function will return a whole year forecast from January to December. For instance, period = c(12,1,2) will retrieve the forecast for the standard boreal winter (DJF), period = 6:8 for summer (JJA) and so on.
- years: Optional vector of years to select. Default to all available years. Note that in the case of a year-crossing season for a particular year period (e.g. winter DJF, season = c(12,1,2) and years = 1981:2000), by convention the first season returned will be DJF 1980/81, if available (otherwise a warning message is given).
- leadMonth: Lead month forecast time corresponding to the first month of the specified season. Note that leadMonth = 1 for season = 1 (January) corresponds to the December initialization forecasts. The effect of the lead time in the forecast for a particular season can be analyzed by just changing this parameter.

#### Details

Currently, accepted values for the argument var are tas, tasmin, tasmax, pr or mslp, as internally defined in the vocabulary of System4 following the nomenclature displayed in the table below. However, note that new variables and datasets will be progressively included. Further details regarding the nature and temporal aggregation of these variables can be obtained through the dataInventory function.

Short Name	Long name	Units	Instantaneous
tasmax	Maximum temperature at 2 metres	degC	No
tasmin	Minimum temperature at 2 metres	degC	No
tas	Mean temperature at 2 metres	degC	Yes
pr	Total precipitation accumulated	mm	No
mslp	Mean sea level pressure	Pa	Yes

### <u>Value</u>

The output returned by the function consists of a list with the following elements providing the necessary information for data representation and analysis:

- VarName: Character string indicating the variable long name, as defined in the vocabulary (see Table above)
- VarUnits: Character string. Units of the variable, as returned in MemberData
- TimeStep: A difftime class object. Indicates the time span of each forecast time
- MemberData: This is a list of length n, where n = number of members of the ensemble selected by the member argument. Each element of the dataset is a 2-D matrix of i rows x j columns, of i forecast times and j grid-points
- LatLonCoords: A 2-D matrix of j rows (where j = number of grid points selected) and two columns corresponding to the latitude and longitude
  coordinates respectively.
- RunDates: A POSIX1t time object corresponding to the initialization times selected. There is an initialization time associated to each forecast time.
   ForecastDates: A list with two POSIX1t time elements of length i, corresponding to the rows of each matrix in MemberData. The list contain tow elements:
  - Start: Starting times of the verification period of the variable
  - End: End time of the verification period of the variable

### <u>Note</u>

A worked example describing a multi-model selection of a dataset is presented in the tutorial, which can be downloaded <a href="https://examples.new.org/?here">?here</a>, or in the section <a href="https://examples.new.org/?here">Examples?</a>.