

## **Wikiprint Book**

**Title: WRF4Gjihc**

**Subject: TracMeteo - WRF4Gjihc**

**Version: 27**

**Date: 07/07/2022 07:06:55 AM**

## Table of Contents

How to add Neptuno facilities to WRF4G

3

## How to add Neptuno facilities to WRF4G

WRF4G uses [DRM4G](#) to access to different Distributed Resource Managements (DRM) such as:

- PBS/Torque
- SGE
- FORK
- LoadLeveler
- **SLURM**

In order to add new resources, you need to edit [Computing Resources](#) section in the [framework4g.conf](#) file, which is located under `$HOME/WRF4G/etc` directory. The file has to contain one resource per line with the format:

```
resource_name = attributes
...
resource_name = attributes
```

where:

- **resource\_name**: It is the name of the CR.

**attributes**: They are the static attributes of the CR. The syntax is:

```
<scheme>://<username>@<host:port>?<query>
```

**scheme**: URL schemes available are "ssh" and "local".

- **ssh**: In order to connect to remote resource via SSH
- **local**: In order to use a local resource
- **username**: user name on the resource
- **host**: host name
- **port**: host port. By DEFAULT it is 22
- query**: contains additional information of computing resources. The query string syntax is:
  - `key1=value1;key2=value2;key3=value3`

The keys available are:

- **LRMS\_TYPE**(mandatory): Type of LRMS system (**neptuno**)
- **NODECOUNT**(mandatory): Maximum number of job slots for a resource.
- **SSH\_KEY\_FILE**(optional): It defines the key file for "ssh" connection. By DEFAULT it is `~/.ssh/id_rsa`.
- **TEMP\_DIR**(optional): Temporary directory on the resource to store data. By DEFAULT it is `$HOME`. `TEMP_DIR` path must be absolute.
- **RUN\_DIR**(optional): Temporary directory used to run WRF Model on the resource. By DEFAULT it is `$HOME`. `RUN_DIR` path must be absolute.

Example of configuration:

If you want to configure Neptuno facilities using **ssh** protocol, you need to set up SSH login without *password* (see [Appendix B](#)).

In addition, you need to update `WRF4G_BASEPATH`, `WRF4G_DOMAINPATH`, `WRF4G_INPUT` and `WRF4G_APPS` variables, which are defined in [resources.wrf4g](#) file. Due to the fact that these variables may point to other machines. See [running environment](#) for more information.

```
neptuno = ssh://userid@193.144.213.182?LRMS_TYPE=neptuno;NODECOUNT=1500
```

After modifying `ComputingResources` section, WRF4G takes few seconds in order to update the changes